

Eric Conner Design

# **Animatronics Controller**

Eric Conner v2.1.3 September 9, 2019

# **Table of Contents**

Show File Format - XXX.ANI	
Config File Format - FIG.CFG	3
Inputs 0x100 -> 0x1FF	3
Servos 0x200 -> 0x2FF	3
Class Index	4
File Index	5
Class Documentation	6
input_t	6
servo_t	7
File Documentation	8
Animatronics_Controller.ino	8
audio.h	
config.h	10
interface.h	
servo.h	
show.h	
Index	

# **Show File Format - XXX.ANI**

Location	Description
0x0000 - 0xFFDF	Show Data
0xFFE0	Show Number (0xFF)
0xFFE1 - 0xFFE4	Show MS (0xFFFFFFF)
0xFFE5 - 0xFFE7	SPARE
0xFFE8 - 0xFFEF	"©2019ECD"
0xFFF0 - 0xFFFF	Show Name (15 Characters)

# **Config File Format - FIG.CFG**

Location	Description
0x000 - 0x00F	Figure Name (16 Characters)
0x010 - 0x0F7	SPARE
0x0F8 - 0x0FF	"©2019ECD"

# Inputs 0x100 -> 0x1FF

Location	Description
0x1X0	Input Enabled (0xFF)
0x1X1	Input Pin (0xFF)
0x1X2 - 0x1X3	Input Min (0xFFFF)
0x1X4 - 0x1X5	Input Max (0xFFFF)
0x1X6 - 0x1X7	SPARE
0x1X8 - 0x1XF	Input Name (8 Characters)

## **Servos 0x200 -> 0x2FF**

Location	Description
0x2X0	Servo Enabled (0xFF)
0x2X1	Servo Pin (0xFF)
0x2X2 - 0x2X3	Servo Min (0xFFFF)
0x2X4 - 0x2X5	Servo Max (0xFFFF)
0x2X6	Servo Input (0xFF)
0x2X7	Servo Invert (0xFF)
0x2X8 - 0x2XF	Servo Name (8 Characters)

# **Class Index**

# **Class List**

Here are the classes, structs, unions and in	nterfaces with brief descriptions:
<pre>input_t (Struct for Input settings )</pre>	
<pre>servo t (Struct for Servo settings )</pre>	

# **File Index**

# **File List**

Here is a list of all documented files with brief descriptions:

Animatronics Controller.ino (A custom Animatronics Controller with the ability to	load and
save configuration and show files from an SD card in sync with a 16-bit WAV file )	8
audio.h (Functions for playing audio with the PT8211 )	9
config.h (Functions for loading, saving and modifying the config file )	10
interface.h (Functions for getting data from the serial buffer )	13
servo.h (Functions for working with the servos )	14
show.h (Functions for creating, loading, saving, recording and playing a show file )	16

# **Class Documentation**

# input\_t Struct Reference

Struct for Input settings.

## **Public Attributes**

- bool enabled
- uint8\_t **pin**
- uint16\_t min
- uint16\_t max
- uint16\_t value

The documentation for this struct was generated from the following file:

• servo.h

# servo\_t Struct Reference

Struct for Servo settings.

## **Public Attributes**

- bool enabled
- uint8\_t **pin**
- uint16\_t min
- uint16\_t max
- uint16\_t value
- <u>input\_t</u> input
- bool invert

The documentation for this struct was generated from the following file:

• <u>servo.h</u>

# **File Documentation**

## Animatronics\_Controller.ino File Reference

A custom Animatronics Controller with the ability to load and save configuration and show files from an SD card in sync with a 16-bit WAV file.

### **Macros**

- #define INTERFACE\_PIN 28
- #define **TEST\_PIN** 29

## **Functions**

- void <u>setup</u> ()
  Setup the Animatronics Controller.
- void <u>loop</u> ()
   Main program loop, load each show file and play it.
- void <u>mainMenu</u> () *Main menu*.
- void <u>loadedShowMenu</u> ()

  Loaded show menu.
- void <u>configMenu</u> () Config menu.

## **Variables**

• char **versionNumber** [] = "2.1.3"

## audio.h File Reference

Functions for playing audio with the PT8211.

## **Functions**

- void <u>setupAudio</u> (void)

  Setup audio output (Note: This is required)
- uint32\_t <u>getAudioMS</u> (void)
   Get the length of WAV file associated with the loaded show in milliseconds.
- void <u>playAudio</u> (void)
   Play WAV file associated with the loaded show.
- void <u>stopAudio</u> (void)
   Stop playing WAV file.

## **Function Documentation**

## uint32\_t getAudioMS (void )

#### Returns

Returns the length of the loaded audio file in milliseconds, 0 ... 4294967295

## config.h File Reference

Functions for loading, saving and modifying the config file.

### **Functions**

- void <u>loadConfig</u> (void)
   Load the config file from SD card.
- void <u>saveConfig</u> (void)

  Save the config file to the SD card.
- char \* <u>getFigureName</u> (void)

  Get the figure name from the config file.
- char \* <u>getInputName</u> (uint8\_t number)
   Get the input name for a given number from the config file.
- void <u>setInputName</u> (uint8\_t number, char \*name)

  Set the input name for a given number from the config file.
- char \* <u>getServoName</u> (uint8\_t number)

  Get the servo name for a given number from the config file.
- void <u>setServoName</u> (uint8\_t number, char \*name)

  Set the servo name for a given number from the config file.
- <u>input t getInputData</u> (uint8\_t number)

  Get the input data for a given input number.
- <u>servo\_t getServoData</u> (uint8\_t number)

  Get the servo data for a given servo number.
- uint16\_t <u>getServoCenter</u> (uint8\_t number) Get the center position for a given servo.
- uint16\_t \* minmaxInput (uint8\_t input)

  Configure Input Min / Max.
- void <u>configInput</u> (uint8\_t number) Configure a given input.
- void <u>configServo</u> (uint8\_t number) Configure a given servo.

- void <u>invertServo</u> (uint8\_t number) *Invert a given servo*.
- void <u>toggleServo</u> (uint8\_t number) Enable/Disable a given servo.

## **Function Documentation**

## void configInput (uint8\_t number)

#### **Parameters**

number	Input number, 0 15

## void configServo (uint8\_t number)

#### **Parameters**

numi	ber	Servo number, 0 15

## char\* getFigureName (void)

### **Returns**

Returns the figure name as a char[16]

## input\_t getInputData (uint8\_t number)

#### **Parameters**

_		
	number	Input number, 0 15

#### **Returns**

Returns a input\_t struct

## char\* getInputName (uint8\_t number)

### **Parameters**

number	Input number, 0 15	
--------	--------------------	--

#### **Returns**

Returns the input name for a given number as a char[8]

## uint16\_t getServoCenter (uint8\_t number)

#### **Parameters**

number	Servo number, 0 15
--------	--------------------

### **Returns**

Returns a uint16\_t for the center position of a given servo

## servo\_t getServoData (uint8\_t number)

### **Parameters**

number	Servo number, 0 15

### Returns

Returns a servo\_t struct

## char\* getServoName (uint8\_t number)

#### **Parameters**

number	Servo number, 0 15
--------	--------------------

### Returns

Returns the servo name for a given number as a char[8]

## void invertServo (uint8\_t number)

#### **Parameters**

number Servo number, 0 15
---------------------------

## uint16\_t\* minmaxInput (uint8\_t input)

#### **Parameters**

1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1	
input   Input pin to read, 0 15	

#### Returns

Returns the Input Min / Max as uint16\_t array, 0 ... 1023

## void setInputName (uint8\_t number, char \* name)

#### **Parameters**

number	Input number, 0 15
name	Input name, char[8]

## void setServoName (uint8\_t number, char \* name)

#### **Parameters**

_		
	number	Servo number, 0 15
	name	Servo name, char[8]

## void toggleServo (uint8\_t number)

### **Parameters**

number	Servo number, 0 15	
--------	--------------------	--

## interface.h File Reference

Functions for getting data from the serial buffer.

## **Functions**

- char <u>getChar</u> (void)

  Get a char from the serial buffer.
- uint32\_t <u>getInt</u> (void)

  Get a uint32\_t from the serial buffer.
- char \* getString (void)
   Get char[16] from the serial buffer.

## **Function Documentation**

## char getChar (void )

### Returns

Returns a char from the serial buffer

## uint32\_t getInt (void )

#### Returns

Returns a uint32\_t from the serial buffer

## char\* getString (void )

### **Returns**

Returns a char[16] from the serial buffer

## servo.h File Reference

Functions for working with the servos.

### Classes

- struct <u>input\_t</u>

  Struct for Input settings.
- struct <u>servo\_t</u>
   Struct for Servo settings.

### **Functions**

- void <u>setupServos</u> (void)
   Setup the servo output (Note: This is required)
- void <u>processInputs</u> (void)
   Load input data from the config file to an array.
- uint8\_t <u>getInputCount</u> (void)

  Get the total number of inputs from the config file.
- void <u>processServos</u> (void)
   Load servo data from the config file to an array.
- uint8\_t <u>getServoCount</u> (void)

  Get the total number of servos from the config file.
- void <u>centerServos</u> (void)

  Move all enabled servos to the center position.
- void <u>updateServo</u> (uint8\_t number)

  Read a given servo input and update its position.
- uint16\_t <u>minmaxServo</u> (uint8\_t pin, uint8\_t servo) Configure servo Min/Max.
- void <u>recordServo</u> (uint8\_t number)

  Read a given servo input, save it to the show file and update its position.
- void <u>playServo</u> (uint8\_t number)

  Read a given servo from the show file and update its position.

## **Function Documentation**

## uint8\_t getInputCount (void )

### Returns

Returns the total number of inputs, 0 ... 15

## uint8\_t getServoCount (void )

### Returns

Returns the total number of servos, 0 ... 15

## uint16\_t minmaxServo (uint8\_t pin, uint8\_t servo)

#### **Parameters**

pin	Input pin to read, 0 15
servo	Servo pin to write, 0 15

#### **Returns**

Returns the servo position as uint16\_t, 150 ... 600

## void playServo (uint8\_t number)

### **Parameters**

number	Servo number to play, 0 15

## void recordServo (uint8\_t number)

#### **Parameters**

number	Servo number to record, 0 15
--------	------------------------------

## void updateServo (uint8\_t number)

### **Parameters**

|--|

## show.h File Reference

Functions for creating, loading, saving, recording and playing a show file.

### **Functions**

- void <u>newShow</u> (void)

  Create a new show file, calls record after the file is created.
- bool <u>loadShow</u> (uint8\_t number)

  Load a given show file from SD card.
- void <u>saveShow</u> (void)

  Save show file to SD card.
- void <u>deleteShow</u> (void)
   Delete show file from SD card.
- void <u>playShow</u> (void) Play the loaded show.
- void <u>recordShow</u> (void) *Record show*.
- void <u>testShow</u> (void) *Test servo function*.
- uint8\_t <u>getShowNumber</u> (void)

  Get the loaded show number.
- void <u>setShowNumber</u> (uint8\_t number) *Set the show number.*
- uint32\_t <u>getShowMS</u> (void)

  Get the length of the show in milliseconds.
- void <u>setShowMS</u> (uint32\_t ms)

  Set the length of the show in milliseconds.
- char \* <u>getShowName</u> (void)

  Get the show name.
- void <u>setShowName</u> (char \*name)

  Set the show name.

- void <u>saveData</u> (uint32\_t address, uint8\_t data) *Brief description*.
- uint8\_t <u>getData</u> (uint32\_t address)

  Get data from show file.
- uint32\_t <u>getShowFrameCount</u> (void) Get the current show frame.
- uint32\_t <u>getShowMaxFrameCount</u> (void) Get the max show frame.

## **Function Documentation**

### uint8\_t getData (uint32\_t address)

#### **Parameters**

addres.	r A	Address to read data from, 0x0000 0xFFE0
---------	-----	--

#### **Returns**

Returns data from address, 0 ... 255

### uint32\_t getShowFrameCount (void )

#### Returns

Returns the current show frame count, 0x0000 ... 0xFFE0

## uint32\_t getShowMaxFrameCount (void )

#### Returns

Returns the max show frame, 0x0000 ... 0xFFE0

## uint32\_t getShowMS (void )

#### **Returns**

Returns the show length in milliseconds, 0 ... 4294967295

## char\* getShowName (void )

#### **Returns**

Returns the show name as a char[16]

## uint8\_t getShowNumber (void )

### **Returns**

Returns the loaded show number, 0 ... 255

## bool loadShow (uint8\_t number)

### **Parameters**

number	0 255
--------	-------

### Returns

true if show loaded and false if there was an error

## void saveData (uint32\_t address, uint8\_t data)

### **Parameters**

address	Address to write data to, 0x0000 0xFFE0	
data	Data to write, 0 255	

## void setShowMS (uint32\_t ms)

#### **Parameters**

ms	Show length in milliseconds, 0 4294967295	
----	---	--

## void setShowName (char \* name)

### **Parameters**

name	Name of show to write to file
------	-------------------------------

## void setShowNumber (uint8\_t number)

### **Parameters**

number	Show number, 0 255

# Index

IIIGEX	
Animatronias Controllar ino 9	show h 17
Animatronics_Controller.ino, 8	show.h, 17
audio.h, 9	getShowNumber
getAudioMS, 9	show.h, 17
config.h, 10	getString
configInput, 11	interface.h, 13
configServo, 11	input_t, 6
getFigureName, 11	interface.h, 13
getInputData, 11	getChar, 13
getInputName, 11	getInt, 13
getServoCenter, 11	getString, 13
getServoData, 12	invertServo
getServoName, 12	config.h, 12
invertServo, 12	loadShow
minmaxInput, 12	show.h, 18
setInputName, 12	minmaxInput
setServoName, 12	config.h, 12
toggleServo, 12	minmaxServo
configInput	servo.h, 15
config.h, 11	playServo
configServo	servo.h, 15
config.h, 11	recordServo
getAudioMS	servo.h, 15
audio.h, 9	saveData
getChar	show.h, 18
interface.h, 13	servo.h, 14
getData	getInputCount, 15
show.h, 17	getServoCount, 15
getFigureName	minmaxServo, 15
config.h, 11	playServo, 15
getInputCount	recordServo, 15
servo.h, 15	updateServo, 15
getInputData	servo_t, 7
config.h, 11	setInputName
getInputName	config.h, 12
config.h, 11	setServoName
getInt	config.h, 12
interface.h, 13	setShowMS
getServoCenter	show.h, 18
config.h, 11	setShowName
getServoCount	show.h, 18
servo.h, 15	setShowNumber
getServoData	show.h, 18
config.h, 12	show.h, 16
getServoName	getData, 17
config.h, 12	getShowFrameCount, 17
getShowFrameCount	getShowMaxFrameCount, 17
show.h, 17	getShowMS, 17
getShowMaxFrameCount	getShowName, 17
show.h, 17	getShowNumber, 17
getShowMS	loadShow, 18
show.h, 17	saveData, 18
getShowName	setShowMS, 18

setShowName, 18 setShowNumber, 18 toggleServo config.h, 12 updateServo servo.h, 15