

EricConner.net

# **Animatronics Controller**

V2.2.2 January 29, 2020

# **Table of Contents**

Show File Format - XXX.ANI	
Config File Format - FIG.CFG	2
Inputs 0x100 -> 0x1FF	
Servos 0x200 -> 0x2FF	
Servo Filter Values 0x300 -> 0x30F	
Class Index	
File Index	
Class Documentation	
input_t	
servo t	
File Documentation	
Animatronics_Controller.ino	
audio.h	
config.h	9
interface.h	
servo.h	
show.h	
Index	-

# **Show File Format - XXX.ANI**

Location	Description
0x0000 - 0xFFDF	Show Data
0xFFE0	Show Number (0xFF)
0xFFE1 - 0xFFE4	Show MS (0xFFFFFFF)
0xFFE5 - 0xFFE7	SPARE
0xFFE8 - 0xFFEF	"©YYYY EC"
0xFFF0 - 0xFFFF	Show Name (15 Characters)

# **Config File Format - FIG.CFG**

Location	Description
0x000 - 0x00F	Figure Name (16 Characters)
0x010 - 0x0F7	SPARE
0x0F8 - 0x0FF	"©YYYY EC"

# Inputs 0x100 -> 0x1FF

Location	Description
0x1X0	Input Enabled (0xFF)
0x1X1	Input Pin (0xFF)
0x1X2 - 0x1X3	Input Min (0xFFFF)
0x1X4 - 0x1X5	Input Max (0xFFFF)
0x1X6 - 0x1X7	SPARE
0x1X8 - 0x1XF	Input Name (8 Characters)

## **Servos 0x200 -> 0x2FF**

Location	Description
0x2X0	Servo Enabled (0xFF)
0x2X1	Servo Pin (0xFF)
0x2X2 - 0x2X3	Servo Min (0xFFFF)
0x2X4 - 0x2X5	Servo Max (0xFFFF)
0x2X6	Servo Input (0xFF)
0x2X7	Servo Invert (0xFF)
0x2X8 - 0x2XF	Servo Name (8 Characters)

## Servo Filter Values 0x300 -> 0x30F

Location	Description
0x30X	Servo Filter Value (0xFF)

# **Class Index**

# **Class List**

Here are the classes, structs, unions and in	nterfaces with brief descriptions:
<pre>input_t (Struct for Input settings )</pre>	
servo t (Struct for Servo settings )	

# File Index

## **File List**

Here is a list of all documented files with brief descriptions:

Animatronics Controller.ino (A custom Animatronics Controller with the ability to	load and save
configuration and show files from an SD card in sync with a 16-bit WAV file )	7
audio.h (Functions for playing audio with the PT8211 )	8
config.h (Functions for loading, saving and modifying the config file )	9
interface.h (Functions for getting data from the serial buffer )	12
servo.h (Functions for working with the servos )	13
show.h (Functions for creating, loading, saving, recording and playing a show file )	15

# **Class Documentation**

# input\_t Struct Reference

Struct for Input settings.

## **Public Attributes**

- bool enabled
- uint8\_t **pin**
- uint16\_t min
- uint16\_t max
- uint16\_t value

The documentation for this struct was generated from the following file:

• servo.h

## servo\_t Struct Reference

Struct for Servo settings.

## **Public Attributes**

- bool enabled
- uint8\_t **pin**
- uint16\_t **min**
- uint16\_t **max**
- uint16\_t value
- uint8\_t **filter**
- input t input bool invert

The documentation for this struct was generated from the following file:

• servo.h

## **File Documentation**

## Animatronics\_Controller.ino File Reference

A custom Animatronics Controller with the ability to load and save configuration and show files from an SD card in sync with a 16-bit WAV file.

#### **Macros**

- #define **INTERFACE\_PIN** 28
- #define **TEST\_PIN** 29

## **Functions**

- void <u>setup</u> ()
  Setup the Animatronics Controller.
- void <u>loop</u> ()
   Main program loop, load each show file and play it.
- void <u>mainMenu</u> () *Main menu*.
- void <u>loadedShowMenu</u> ()

  Loaded show menu.
- void <u>configMenu</u> () Config menu.

## **Variables**

• char **versionNumber** [] = "2.2.2"

## audio.h File Reference

Functions for playing audio with the PT8211.

## **Functions**

- void <u>setupAudio</u> (void)

  Setup audio output (Note: This is required)
- uint32\_t <u>getAudioMS</u> (void)

  Get the length of WAV file associated with the loaded show in milliseconds.
- void <u>playAudio</u> (void)
   Play WAV file associated with the loaded show.
- void <u>stopAudio</u> (void) Stop playing WAV file.

## **Function Documentation**

uint32\_t getAudioMS (void )

#### **Returns**

Returns the length of the loaded audio file in milliseconds, 0 ... 4294967295

## config.h File Reference

Functions for loading, saving and modifying the config file.

#### **Functions**

- void <u>loadConfig</u> (void)

  Load the config file from SD card.
- void <u>saveConfig</u> (void)

  Save the config file to the SD card.
- char \* getFigureName (void)
   Get the figure name from the config file.
- char \* <u>getInputName</u> (uint8\_t number)

  Get the input name for a given number from the config file.
- void <u>setInputName</u> (uint8\_t number, char \*name)

  Set the input name for a given number from the config file.
- char \* <u>getServoName</u> (uint8\_t number)

  Get the servo name for a given number from the config file.
- void <u>setServoName</u> (uint8\_t number, char \*name)

  Set the servo name for a given number from the config file.
- <u>input t getInputData</u> (uint8\_t number)

  Get the input data for a given input number.
- <u>servo t getServoData</u> (uint8\_t number)

  Get the servo data for a given servo number.
- uint16\_t <u>getServoCenter</u> (uint8\_t number)

  Get the center position for a given servo.
- uint16\_t \* minmaxInput (uint8\_t input)

  Configure Input Min / Max.
- void <u>configInput</u> (uint8\_t number) Configure a given input.
- void <u>configServo</u> (uint8\_t number) Configure a given servo.
- void <u>invertServo</u> (uint8\_t number) *Invert a given servo*.
- void <u>filterServo</u> (uint8\_t number)

Change filter value for a given servo.

• void <u>toggleServo</u> (uint8\_t number) Enable/Disable a given servo.

## **Function Documentation**

## void configInput (uint8\_t number)

#### **Parameters**

number	Input number, 0 15
--------	--------------------

## void configServo (uint8\_t number)

#### **Parameters**

number	Servo number, 0 15
TUTTOCT	Servo number, 0 13

## void filterServo (uint8\_t number)

#### **Parameters**

number	Servo number, 0 15

## char\* getFigureName (void )

#### **Returns**

Returns the figure name as a char[16]

## input t getInputData (uint8\_t number)

## **Parameters**

number	Input number, 0 15
TUTTIOCT	input number, 0 15

## Returns

Returns a input\_t struct

## char\* getInputName (uint8\_t number)

#### **Parameters**

number	Input number, 0 15

#### **Returns**

Returns the input name for a given number as a char[8]

## uint16\_t getServoCenter (uint8\_t number)

•			
	number	Servo number, 0 15	

## Returns

Returns a uint16\_t for the center position of a given servo

## servo t getServoData (uint8\_t number)

#### **Parameters**

	T
number	Servo number, 0 15

#### **Returns**

Returns a servo\_t struct

## char\* getServoName (uint8\_t number)

#### **Parameters**

number Servo number, 0 15	
---------------------------	--

#### **Returns**

Returns the servo name for a given number as a char[8]

## void invertServo (uint8\_t number)

#### **Parameters**

number Servo number, 0 15
---------------------------

## uint16\_t\* minmaxInput (uint8\_t input)

#### **Parameters**

input	Input pin to read, 0 15

#### **Returns**

Returns the Input Min / Max as uint16\_t array, 0 ... 1023

## void setInputName (uint8\_t number, char \* name)

## **Parameters**

number	Input number, 0 15
name	Input name, char[8]

## void setServoName (uint8\_t number, char \* name)

#### **Parameters**

number	Servo number, 0 15
name	Servo name, char[8]

## void toggleServo (uint8\_t number)

-		
	number	Servo number, 0 15

## interface.h File Reference

Functions for getting data from the serial buffer.

## **Functions**

- char <u>getChar</u> (void) *Get a char from the serial buffer.*
- uint32\_t <u>getInt</u> (void)

  Get a uint32\_t from the serial buffer.
- char \* getString (void)

  Get char[16] from the serial buffer.

## **Function Documentation**

## char getChar (void )

#### Returns

Returns a char from the serial buffer

## uint32\_t getInt (void)

#### **Returns**

Returns a uint32\_t from the serial buffer

## char\* getString (void )

#### **Returns**

Returns a char[16] from the serial buffer

## servo.h File Reference

Functions for working with the servos.

#### **Classes**

- struct <u>input\_t</u>
  Struct for Input settings.
- struct <u>servo\_t</u>
   Struct for Servo settings.

## **Functions**

- void <u>setupServos</u> (void)

  Setup the servo output (Note: This is required)
- void <u>processInputs</u> (void)

  Load input data from the config file to an array.
- uint8\_t <u>getInputCount</u> (void)

  Get the total number of inputs from the config file.
- void <u>processServos</u> (void)

  Load servo data from the config file to an array.
- uint8\_t <u>getServoCount</u> (void)

  Get the total number of servos from the config file.
- void <u>centerServos</u> (void)

  Move all enabled servos to the center position.
- void <u>updateServo</u> (uint8\_t number)

  Read a given servo input and update its position.
- uint16\_t <u>minmaxServo</u> (uint8\_t pin, uint8\_t servo) Configure servo Min/Max.
- void <u>recordServo</u> (uint8\_t number)

  Read a given servo input, save it to the show file and update its position.
- void <u>playServo</u> (uint8\_t number)

  Read a given servo from the show file and update its position.
- float <u>filter</u> (float servoValue, float inputValue, int filter) Filter servo value for smoothing.

## **Function Documentation**

## float filter (float servoValue, float inputValue, int filter)

#### **Parameters**

servoValue	@Todo
inputValue	@Todo
filter	@Todo

#### Returns

Returns filtered servo value

## uint8\_t getInputCount (void )

#### Returns

Returns the total number of inputs, 0 ... 15

## uint8\_t getServoCount (void )

## Returns

Returns the total number of servos, 0 ... 15

## uint16\_t minmaxServo (uint8\_t pin, uint8\_t servo)

## **Parameters**

pin	Input pin to read, 0 15
servo	Servo pin to write, 0 15

#### **Returns**

Returns the servo position as uint16\_t, 150 ... 600

## void playServo (uint8\_t number)

#### **Parameters**

number Servo number to play, 0 15	
-----------------------------------	--

## void recordServo (uint8\_t number)

#### **Parameters**

number	Servo number to record, 0 15

## void updateServo (uint8\_t number)

-		
	number	Servo number to update, 0 15

## show.h File Reference

Functions for creating, loading, saving, recording and playing a show file.

## **Functions**

- void <u>newShow</u> (void)
   Create a new show file, calls record after the file is created.
- bool <u>loadShow</u> (uint8\_t number)

  Load a given show file from SD card.
- void <u>saveShow</u> (void) Save show file to SD card.
- void <u>deleteShow</u> (void)
   Delete show file from SD card.
- void <u>playShow</u> (void)
   Play the loaded show.
- void <u>recordShow</u> (void) *Record show*.
- void <u>testShow</u> (void) *Test servo function*.
- uint8\_t <u>getShowNumber</u> (void)

  Get the loaded show number.
- void <u>setShowNumber</u> (uint8\_t number) *Set the show number.*
- uint32\_t <u>getShowMS</u> (void)

  Get the length of the show in milliseconds.
- void <u>setShowMS</u> (uint32\_t ms)

  Set the length of the show in milliseconds.
- char \* <u>getShowName</u> (void)

  Get the show name.
- void <u>setShowName</u> (char \*name) Set the show name.
- void <u>saveData</u> (uint32\_t address, uint8\_t data)
   Brief description.
- uint8\_t <u>getData</u> (uint32\_t address)

Get data from show file.

- uint32\_t <u>getShowFrameCount</u> (void) Get the current show frame.
- uint32\_t <u>getShowMaxFrameCount</u> (void) *Get the max show frame.*

## **Function Documentation**

## uint8\_t getData (uint32\_t address)

#### **Parameters**

address	Address to read data from, 0x0000 0xFFE0
---------	--

#### **Returns**

Returns data from address, 0 ... 255

## uint32\_t getShowFrameCount (void )

#### Returns

Returns the current show frame count, 0x0000 ... 0xFFE0

## uint32\_t getShowMaxFrameCount (void )

#### **Returns**

Returns the max show frame, 0x0000 ... 0xFFE0

#### uint32\_t getShowMS (void )

#### **Returns**

Returns the show length in milliseconds,  $0 \dots 4294967295$ 

## char\* getShowName (void )

#### **Returns**

Returns the show name as a char[16]

## uint8\_t getShowNumber (void )

#### **Returns**

Returns the loaded show number, 0 ... 255

## bool loadShow (uint8\_t number)

## **Parameters**

#### Returns

true if show loaded and false if there was an error

## void saveData (uint32\_t address, uint8\_t data)

## **Parameters**

address	Address to write data to, 0x0000 0xFFE0
data	Data to write, 0 255

## void setShowMS (uint32\_t ms)

## **Parameters**

ms	Show length in milliseconds, 0 4294967295

## void setShowName (char \* name)

## **Parameters**

name	Name of show to write to file
------	-------------------------------

## void setShowNumber (uint8\_t number)

number	Show number, 0 255
--------	--------------------

# Index

Animatronics_Controller.ino, 7	getShowNumber
audio.h, 8	show.h, 16
getAudioMS, 8	getString
config.h, 9	interface.h, 12
configInput, 10	input_t, 5
configServo, 10	interface.h, 12
filterServo, 10	getChar, 12
getFigureName, 10	getInt, 12
getInputData, 10	getString, 12
getInputName, 10	invertServo
getServoCenter, 10	config.h, 11
getServoData, 11	loadShow
getServoName, 11	show.h, 16
invertServo, 11	minmaxInput
minmaxInput, 11	config.h, 11
setInputName, 11	minmaxServo
setServoName, 11	servo.h, 14
toggleServo, 11	playServo
configInput	servo.h, 14
config.h, 10	recordServo
configServo	servo.h, 14
config.h, 10	saveData
filter	show.h, 17
servo.h, 14	servo.h, 13
filterServo	filter, 14
config.h, 10	getInputCount, 14
getAudioMS	getServoCount, 14
audio.h, 8	minmaxServo, 14
getChar	playServo, 14
interface.h, 12	recordServo, 14
getData	updateServo, 14
show.h, 16	servo_t, 6
getFigureName	setInputName
config.h, 10	config.h, 11
getInputCount	setServoName
servo.h, 14	config.h, 11
getInputData	setShowMS
config.h, 10	show.h, 17
getInputName	setShowName
config.h, 10	show.h, 17
getInt	setShowNumber
interface.h, 12	show.h, 17
getServoCenter	show.h, 15
config.h, 10	getData, 16
<u> </u>	getShowFrameCount, 16
getServoCount	
servo.h, 14	getShowMs_16
getServoData	getShowMS, 16
config.h, 11	getShowName, 16
getServoName	getShowNumber, 16
config.h, 11	loadShow, 16
getShowFrameCount	saveData, 17
show.h, 16	setShowMS, 17
getShowMaxFrameCount	setShowName, 17
show.h, 16	setShowNumber, 17
getShowMS	toggleServo
show.h, 16	config.h, 11
getShowName	updateServo
show.h, 16	servo.h, 14